Disabling NetBIOS Tutorial By Eric M. Bouse 3/2004

1. Right click on "My Network Places" on the desktop and choose Properties.



2. Right click on "Local Area Connection" and choose Properties.



3. Left click on TCP/IP and then click the Properties button.

. 1 - F		
neral Sharing Au	thentication	
onnect using:		
😲 3Com 3C920 In	tegrated Fast Ethernet	Controller (3C905C-
		Configure
omponents checked	are used by this conne	ection:
🛛 🖳 Novell Client fi	or Windows	
🗹 🔜 Client for Micro	osoft Networks	
🛛 📃 Virtual Machin	e Network Services	
Internet Protor	col (TCP/IP)	
	-	
Install	Uninstall	Properties
Description		
Description		stocol. The default
Transmission Contro wide area network j across diverse inter	ol Protocol/Internet Pro protocol that provides (connected networks,	communication
Transmission Contro wide area network p across diverse inter	of Protocol/Internet Pro protocol that provides (connected networks,	communication
Transmission Contri wide area network j across diverse inter Show icon in taskt	of Protocol/Internet Pro protocol that provides (connected networks, par when connected	communication
Transmission Contri wide area network j across diverse inter	of Protocol/Internet Pro protocol that provides (connected networks,	communication

4. Click on the Advanced button.

ernet Protocol (TCP/IP) Prop	erties
ieneral	
You can get IP settings assigned this capability. Otherwise, you nee the appropriate IP settings.	automatically if your network supports d to ask your network administrator fo
Obtain an IP address autom	atically
C Use the following IP address	1 2
IP address:	14 14 14 14 14 14 14 14 14 14 14 14 14 1
Subnet mask:	17 17 7
Default gateway:	1 1 1 1 1
Obtain DNS server address	automatically
- C Use the following DNS serve	er addresses:
Preferred DNS server:	1 1 2
Alternate DNS server:	
	25

5. Select the "WINS" tab.

D

Automotion in a	rea Connection Properties	<u>? × </u>
Gener	ral Sharing Authentication	
C	¥ 4	
[In	ternet Protocol (TCP/IP) Properties	? ×
1 F	Advanced TLP/IP Settings	<u> </u>
	IP Settings DNS WINS Options	
C	-WINS addresses, in order of use:	
Γ	F	
		Î
		5
1		
	Add Edit	Remove
-	Add Edit	Remove
	Add Edit	Remove
l l	Add Edit	Remove
	Add Edit If LMHOSTS lookup is enabled, it applies to TCP/IP is enabled.	Remove all connections for which
-	Add Edit If LMHOSTS lookup is enabled, it applies to TCP/IP is enabled. Enable LMHOSTS lookup	A all connections for which
 	Add Edit If LMHOSTS lookup is enabled, it applies to TCP/IP is enabled. If Enable LMHOSTS lookup	Remove all connections for which Import LMHOSTS
 	Add Edit If LMHOSTS lookup is enabled, it applies to TCP/IP is enabled. Enable LMHOSTS lookup Enable NetBIOS over TCP/IP	A all connections for which
- - - -	Add Edit If LMHOSTS lookup is enabled, it applies to TCP/IP is enabled. Enable LMHOSTS lookup Enable NetBIOS over TCP/IP Disable NetBIOS over TCP/IP	e all connections for which



6. Select the "Disable NetBIOS over TCP/IP" radio button. At this point you may click OK a few times to close out each window. Changes will be in effect after next computer restart.

et Protoc vanced T(ol (TCP/IP) Properties P/IP Settings	
Settings	DNS WINS Options	
⊢WINS ac	ddresses, in order of use:	
If LMHOST TCP/IP is	FS lookup is enabled, it applies enabled.	s to all connections for whic
🔽 Enable	LMHOSTS lookup	Import LMHOS1
C Enable	NetBIOS over TCP/IP	
🖲 Disable	NetBIOS over TCP/IP	
	etBLOS setting from the DHCP	server